



B144

CABEL NECK VEST
USING
CASCADE
“BOLLICINI” REVOLUTION YARN



DESIGNED BY
YVETTE SILVERMAN

Cabled Neck Open Vest

Designed by Yvette Silverman for Cascade Yarns

Knitted Measurements

Bust 34-36 (38-40, 42-44) in

Length 25 ½ (26 ½, 27 ½) in

Materials 8 (9, 10) balls each approx. 87yds of Cascade Yarns Bollicine Revolution, 90% Merino Wool, 10% polyamid, one pair # 13 knitting needles or size to obtain gauge, 1 size G crochet needle, 1 cable needle

Gauge 12 sts & 17 ½ rows = 4 in. Take time to check gauge

Pattern Cable Pattern = 10 sts

Row 1 (WS) K2, P 6, K2

Row 2 (RS) P2 K2 sl 2 WYIB, k2, P2

Row 3 K2, P2, sl 2 WYIF, P2, K 2

Row 4 P2, sl next 2 sts to cn hold in back, K1, then K 2 from cn, sl next st, to cn hold in front, K 2 then ,then K 1 from cn, P2

Repeat 4 rows for cable patt

Note start cast on of sleeve armbands in cable patt for fronts same as for the back,& bind off in same row of cable patt for front shoulders as for back.

Back With # 13 needle cast on 50 (54, 58) sts. Work in K1 P1 rib for 3 rows. Beg cable patt on (WS) with row 1 as follows: P 20 (22, 24) sts, cable patt next 10 sts, P 20 (22, 24) sts Continue this way working the stock sts & the center cable patt sts till piece measures 17 (18, 19) in from the beg, or desired length to armbands.

Armbands Cast on 10 sts at the beg of the next row, work across back as established, inc 10 sts at the end of the row for other armband. Beg cable patt on armbands as the same row of center back cable. Work in this manner till armbands measure 8 ½ (9, 9 ! /2) in from beg . Bind off all sts in patt.

Left Front Cast on 26 (30, 34) st. Work in rib as for back.

Row 1 (WS) work 10 sts in cable patt, P across row. Cable patt at front edge. Cont patt as for back working the cable patt at front edge & stock st the remaining sts. Inc armbands on the same patt row as for back & bind off on the same patt row as for back at the shoulder.

Right Front Work as for left front reversing all shaping.

Finishing Block pieces to measurements. Sew shoulder seams, side seams including armband seams. Sew shoulder seams 7 ½ (8, 8 ½) in from armband inward towards neck.

Neckband. Cast on 11 sts. Work 10 sts in cable patt keeping 1 edge st in garter st throughout. Work till piece measures approx 17 (18 19) in to fit around neck. Sew garter st to the neck edge. Work 1 row reverse SC around neckband, armbands & front edge of vest.